

Cinegy Player PRO REST API

Default URL can be changed in EXE.config file. REST host switch in with registry key before Player startup:

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Cinegy LLC\Cinegy\Player]
```

```
"EnableWebApis"=dword:00000001
```

Load media

Name	LoadItem
Method	POST
URL	http://localhost:8123/Player/LoadItem?Path={arg}

Get media

Name	GetCurrentItem
Method	GET
URL	http://localhost:8123/Player/CurrentItem
Message Body	String: Media file path

Get start Timecode

Name	GetCurrentStartTc
Method	GET
URL	http://localhost:8123/Player/StartTc
Message Body	Double: Timecode units

Get IN point

Name	GetCurrentIn
Method	GET
URL	http://localhost:8123/Player/In
Message Body	Double: Timecode units

Set IN point

Name	SetCurrentIn
------	--------------

Method	POST
URL	http://localhost:8123/Player/SetIn?In={arg}

Get OUT point

Name	GetCurrentOut
Method	GET
URL	http://localhost:8123/Player/Out
Message Body	Double: Timecode units

Set OUT point

Name	SetCurrentOut
Method	POST
URL	http://localhost:8123/Player/SetOut?Out={arg}

Get current position

Name	GetCurrentPos
Method	GET
URL	http://localhost:8123/Player/Position
Message Body	Double: TimeCode

Set current position

Name	SetCurrentPos
Method	POST
URL	http://localhost:8123/Player/SetPosition?Pos={arg}

Play media

Name	Play
Method	POST
URL	http://localhost:8123/Player/Play

Pause media

Name	Stop
Method	POST
URL	http://localhost:8123/Player/Stop

Refresh media player

Name	Clear
Method	POST
URL	http://localhost:8123/Player/Clear

Set aspect ratio

Name	SetAspect
Method	POST
URL	http://localhost:8123/Player/SetAspect?Aspect={arg}

Table 1.1: **AspectType** enum members

Origin
Aspect4X3
Aspect16X9